

LB800 Software Update Instructions

February 2021

For Support: (818) 777-1814

What you will need:

- A USB thumb drive, formatted to (FAT32)
- LB800 - must be powered on




Steps:


1. Download software file to USB thumb drive in the root directory. Do not change the file name. Example: **C2OSInstaller_v1.1.0.0904 (R15 Release).7z**
2. Power LB800 on and insert USB thumb drive.
3. LB800 will identify USB drive and C2OS Installer page will display. Once displayed, select desired update file by using the touch screen.



4. Next, LB800 will display installing page.



5. After the installation is complete, you will receive the "Press OK to reboot." prompt. Remove the USB thumb drive and press OK. You do not need to power cycle the LB800.



LB800 Software Update Instructions

February 2021

For Support: (818) 777-1814

6. To verify your version of software, simply select the version number on the home page and it will display the current versions for the C2 Router & C2OS software

